

[MS-RAA]: Remote Authorization API Protocol

Intellectual Property Rights Notice for Open Specifications Documentation

- **Technical Documentation.** Microsoft publishes Open Specifications documentation for protocols, file formats, languages, standards as well as overviews of the interaction among each of these technologies.
- **Copyrights.** This documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the technologies described in the Open Specifications and may distribute portions of it in your implementations using these technologies or your documentation as necessary to properly document the implementation. You may also distribute in your implementation, with or without modification, any schema, IDL's, or code samples that are included in the documentation. This permission also applies to any documents that are referenced in the Open Specifications.
- **No Trade Secrets.** Microsoft does not claim any trade secret rights in this documentation.
- **Patents.** Microsoft has patents that may cover your implementations of the technologies described in the Open Specifications. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. However, a given Open Specification may be covered by Microsoft [Open Specification Promise](#) or the [Community Promise](#). If you would prefer a written license, or if the technologies described in the Open Specifications are not covered by the Open Specifications Promise or Community Promise, as applicable, patent licenses are available by contacting iplg@microsoft.com.
- **Trademarks.** The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights. For a list of Microsoft trademarks, visit www.microsoft.com/trademarks.
- **Fictitious Names.** The example companies, organizations, products, domain names, email addresses, logos, people, places, and events depicted in this documentation are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

Reservation of Rights. All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

Tools. The Open Specifications do not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them. Certain Open Specifications are intended for use in conjunction with publicly available standard specifications and network programming art, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

Revision Summary

Date	Revision History	Revision Class	Comments
12/16/2011	1.0	New	Released new document.
03/30/2012	1.0	No change	No changes to the meaning, language, or formatting of the technical content.
07/12/2012	1.0	No change	No changes to the meaning, language, or formatting of the technical content.
10/25/2012	1.0	No change	No changes to the meaning, language, or formatting of the technical content.
01/31/2013	2.0	Major	Significantly changed the technical content.
08/08/2013	3.0	Major	Significantly changed the technical content.
11/14/2013	4.0	Major	Significantly changed the technical content.
02/13/2014	5.0	Major	Significantly changed the technical content.

Contents

1 Introduction	5
1.1 Glossary	5
1.2 References	5
1.2.1 Normative References	6
1.2.2 Informative References	6
1.3 Overview	6
1.4 Relationship to Other Protocols	7
1.5 Prerequisites/Preconditions	7
1.6 Applicability Statement	7
1.7 Versioning and Capability Negotiation	7
1.8 Vendor Extensible Fields	8
1.9 Standards Assignments	8
2 Messages	9
2.1 Transport	9
2.2 Common Data Types	9
2.2.1 Data Types	10
2.2.1.1 AUTHZR_HANDLE	10
2.2.2 Enumerations	10
2.2.2.1 AUTHZ_CONTEXT_INFORMATION_CLASS	10
2.2.2.2 AUTHZ_SECURITY_ATTRIBUTE_OPERATION	12
2.2.2.3 AUTHZ_SID_OPERATION	12
2.2.3 Structures	13
2.2.3.1 AUTHZR_ACCESS_REPLY	13
2.2.3.2 AUTHZR_ACCESS_REQUEST	14
2.2.3.3 AUTHZR_CONTEXT_INFORMATION	14
2.2.3.4 AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE	15
2.2.3.5 AUTHZR_SECURITY_ATTRIBUTE_V1	15
2.2.3.6 AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE	16
2.2.3.7 AUTHZR_SECURITY_ATTRIBUTES_INFORMATION	17
2.2.3.8 AUTHZR_SID_AND_ATTRIBUTES	17
2.2.3.9 AUTHZR_TOKEN_GROUPS	17
2.2.3.10 AUTHZR_TOKEN_USER	18
2.2.3.11 SR_SD	18
3 Protocol Details	19
3.1 authzr Server Details	19
3.1.1 Abstract Data Model	19
3.1.2 Timers	19
3.1.3 Initialization	19
3.1.4 Message Processing Events and Sequencing Rules	20
3.1.4.1 AuthzrFreeContext (Opnum 0)	20
3.1.4.2 AuthzrInitializeContextFromSid (Opnum 1)	20
3.1.4.3 AuthzrInitializeCompoundContext (Opnum 2)	22
3.1.4.4 AuthzrAccessCheck (Opnum 3)	23
3.1.4.5 AuthzGetInformationFromContext (Opnum 4)	24
3.1.4.6 AuthzrModifyClaims (Opnum 5)	26
3.1.4.7 AuthzrModifySids (Opnum 6)	28
3.1.5 Timer Events	29
3.1.6 Other Local Events	30

4 Protocol Examples	31
5 Security	34
5.1 Security Considerations for Implementers.....	34
5.2 Index of Security Parameters	34
6 Appendix A: Full IDL	35
7 Appendix B: Product Behavior	38
8 Change Tracking	39
9 Index	41

1 Introduction

This document specifies the Remote Authorization API Protocol. The Remote Authorization API Protocol is a Remote Procedure Call (RPC)-based protocol used to perform various authorization queries on remote computers.

Sections 1.8, 2, and 3 of this specification are normative and can contain the terms MAY, SHOULD, MUST, MUST NOT, and SHOULD NOT as defined in RFC 2119. Sections 1.5 and 1.9 are also normative but cannot contain those terms. All other sections and examples in this specification are informative.

1.1 Glossary

The following terms are defined in [\[MS-GLOS\]](#):

access control list (ACL)
Active Directory
client context
principal self
RPC endpoint
security descriptor
security identifier (SID)
SID
smart card
token
universally unique identifier (UUID)

The following terms are specific to this document:

access control decision: Choosing whether to allow a user access of a resource on a specific remote service based on a given authorization policy.

authorization policy: A set of rules that govern a user's access to one or more resources or classes of resources.

impersonation token: A security context, created on the server, that represents the set of rights and privileges of the user. Used to test whether the user is authorized to access a resource.

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as described in [\[RFC2119\]](#). All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

References to Microsoft Open Specifications documentation do not include a publishing year because links are to the latest version of the documents, which are updated frequently. References to other documents include a publishing year when one is available.

A reference marked "(Archived)" means that the reference document was either retired and is no longer being maintained or was replaced with a new document that provides current implementation details. We archive our documents online [\[Windows Protocol\]](#).

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information.

[C706] The Open Group, "DCE 1.1: Remote Procedure Call", C706, August 1997, <https://www2.opengroup.org/ogsys/catalog/c706>

[MS-DTYP] Microsoft Corporation, "[Windows Data Types](#)".

[MS-ERREF] Microsoft Corporation, "[Windows Error Codes](#)".

[MS-KILE] Microsoft Corporation, "[Kerberos Protocol Extensions](#)".

[MS-LSAT] Microsoft Corporation, "[Local Security Authority \(Translation Methods\) Remote Protocol](#)".

[MS-RPCE] Microsoft Corporation, "[Remote Procedure Call Protocol Extensions](#)".

[MS-SFU] Microsoft Corporation, "[Kerberos Protocol Extensions: Service for User and Constrained Delegation Protocol](#)".

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <http://www.rfc-editor.org/rfc/rfc2119.txt>

1.2.2 Informative References

[MS-GLOS] Microsoft Corporation, "[Windows Protocols Master Glossary](#)".

1.3 Overview

The Remote Authorization API (RAZA) protocol is designed to allow applications to simulate an **access control decision** that would be made when a given principal attempts to access a resource on a remote service that is protected with a given **authorization policy**. Because these are simulations, they can vary from the actual groups and/or claims in a user's **token**.

For example, a user can log on with a password, or the user can log on using a **smart card** (with authentication assurance provisioned). Each type of logon will result in a different kind of **impersonation token**. Logging on using the password produces an impersonation token with a mapped group or claim; logging on using the smart card produces an impersonation token without a mapped group or claim.

The following are some of the examples of this protocol's applications:

- Simulate the groups and/or claims that a user would have if the user were to authenticate to a remote service.
- Simulate a user's access to a hypothetical resource on a specific remote service that is protected with a given authorization policy.
- Simulate how potential changes to the user's group or claim assignments may affect access to resources on the remote machine.

The RAZA protocol defines client and server protocol roles. [<1>](#) A general description of message flow is as follows:

1. The RAZA client initiates a RAZA conversation by issuing a request to a RAZA server to initialize and maintain a resource manager object.
2. The RAZA server listens to an **RPC endpoint**. When a client makes the preceding request, the RAZA server creates and maintains state for a resource manager object on behalf of the client.
3. The RAZA client can then request creation of a **client context** for a user by specifying the user's **security identifier (SID)**. After a client context is successfully created on the server, the RAZA client can examine the contents of the client context (for example, the group SIDs and claims within the client context) and/or modify the client context. Additionally, the RAZA client can perform an "AccessCheck" using the client context and a specified **security descriptor**.

RAZA supports the following method calls to provide clients a way to simulate access control decisions.

- AuthzrFreeContext
- AuthzrInitializeContextFromSid
- AuthzrInitializeCompoundContext
- AuthzrAccessCheck
- AuthzGetInformationFromContext
- AuthzrModifyClaims

1.4 Relationship to Other Protocols

The Remote Authorization API Protocol is dependent on RPC and TCP for its transport.

No other protocol currently depends on the Remote Authorization API Protocol.

1.5 Prerequisites/Preconditions

The Remote Authorization API Protocol is an RPC interface and, as a result, has the prerequisites specified in [\[MS-RPCE\]](#) (section [1.5](#)) as being common to RPC interfaces.

It is assumed that a Remote Authorization API Protocol client has obtained the name of a remote computer that supports the Remote Authorization API Protocol before this protocol is invoked.

1.6 Applicability Statement

This protocol is appropriate only for implementing a tool to remotely approximate and profile "what-if" authorization decisions.

1.7 Versioning and Capability Negotiation

This document covers versioning issues in the following areas:

- **Supported Transports:** This protocol uses multiple RPC Protocol Sequences as specified in section [2.1](#).
- **Security and Authentication Methods:** As specified in [\[MS-RPCE\]](#) section 3.2.1.4.1.

- **Capability Negotiation:** The RAZA protocol does not support negotiation of the interface version to use. Instead, an implementation needs to be configured with the interface version to use.

1.8 Vendor Extensible Fields

This protocol cannot be extended by any party other than Microsoft.

This protocol uses Win32 error codes as defined in [\[MS-ERREF\]](#) section 2.2. Vendors SHOULD reuse those values with their indicated meaning. Choosing any other value runs the risk of a collision in the future.

1.9 Standards Assignments

The following table lists the **universally unique identifier (UUID)** value for the **authzr** interface specified in section [3.1](#).

Parameter	Value	Reference
UUID for authzr	0b1c2170-5732-4e0e-8cd3-d9b16f3b84d7	[C706]

2 Messages

2.1 Transport

This protocol uses the following RPC protocol sequences as specified in [\[MS-RPCE\]](#) (section [2.1.1.1](#) for TCP/IP - NCACN_IP_TCP and section [2.1.1.2](#) for SMB - NCACN_NP):

- RPC over TCP/IP

This protocol uses the following RPC endpoints:

- Dynamic endpoints as specified in [\[C706\]](#) part 4

This protocol MUST use the following UUIDs:

- authzr interface: 0b1c2170-5732-4e0e-8cd3-d9b16f3b84d7
- Object UUIDs: 9a81c2bd-a525-471d-a4ed-49907c0b23da and 5fc860e0-6f6e-4fc2-83cd-46324f25e90b

2.2 Common Data Types

This protocol MUST indicate to the RPC runtime that it is to support both the NDR and NDR64 transfer syntaxes and provide a negotiation mechanism for determining which transfer syntax will be used ([\[MS-RPCE\]](#) section 3.1.1.5.1.1).

The following data types are specified in [\[MS-DTYP\]](#):

Data type name	Section
ACCESS_MASK	2.4.3
BYTE	2.2.6
DWORD	2.2.9
GUID	2.3.4
LARGE_INTEGER	2.3.5
LONG	2.2.27
LONG64	2.2.31
LUID	2.3.7
OBJECT_TYPE_LIST	2.3.9
PVOID	2.2.59
RPC_SID	2.4.2.3
RPC_SID_IDENTIFIER_AUTHORITY	2.4.1.1
SID	2.4.2
SID_IDENTIFIER_AUTHORITY	2.4.1

Data type name	Section
ULONG	2.2.51
ULONG64	2.2.54
USHORT	2.2.58
VOID	2.2.59
WCHAR	2.2.60
WORD	2.2.61

2.2.1 Data Types

This protocol defines the following data type.

Data Type name	Section	Description
AUTHZR_HANDLE	2.2.1.1	Represents an explicit RPC binding handle associated with an authzr interface. Used to maintain security information about a principal.

2.2.1.1 AUTHZR_HANDLE

The AUTHZR_HANDLE data type is used to maintain security information about a principal; it represents an explicit RPC binding handle associated with an authzr interface. This is used to identify the client context when calling methods in this protocol, and the server tracks the AUTHZR_HANDLE for each **ClientContext** ADM element in its **ClientContextList**.

```
typedef [context_handle] PVOID AUTHZR_HANDLE;
```

2.2.2 Enumerations

This protocol uses the following enumeration.

Enumeration name	Section	Description
AUTHZ_CONTEXT_INFORMATION_CLASS	2.2.2.1	References the security attributes of a principal represented by an AUTHZR_HANDLE.
AUTHZ_SECURITY_ATTRIBUTE_OPERATION	2.2.2.2	Identifies operation types on a client context object.
AUTHZ_SID_OPERATION	2.2.2.3	Indicates the type of SID operations that can be made by a call to the AuthzrModifySids method.

2.2.2.1 AUTHZ_CONTEXT_INFORMATION_CLASS

The AUTHZ_CONTEXT_INFORMATION_CLASS enumeration is used to indicate security attributes of a principal represented by an AUTHZR_HANDLE.

```
typedef enum _AUTHZ_CONTEXT_INFORMATION_CLASS {
    AuthzContextInfoUserSid = 1,
    AuthzContextInfoGroupsSids = 2,
    AuthzContextInfoRestrictedSids = 3,
    ReservedEnumValue4 = 4,
    ReservedEnumValue5 = 5,
    ReservedEnumValue6 = 6,
    ReservedEnumValue7 = 7,
    ReservedEnumValue8 = 8,
    ReservedEnumValue9 = 9,
    ReservedEnumValue10 = 10,
    ReservedEnumValue11 = 11,
    AuthzContextInfoDeviceSids = 12,
    AuthzContextInfoUserClaims = 13,
    AuthzContextInfoDeviceClaims = 14,
    ReservedEnumValue15 = 15,
    ReservedEnumValue16 = 16
} AUTHZ_CONTEXT_INFORMATION_CLASS;
```

AuthzContextInfoUserSid: Indicates the principal's user **SID** and its attribute.

AuthzContextInfoGroupsSids: Indicates the groups to which the principal belongs and their attributes.

AuthzContextInfoRestrictedSids: Indicates the restricted SIDs in the principal's security context and their attributes.

ReservedEnumValue4: Not used.

ReservedEnumValue5: Not used.

ReservedEnumValue6: Not used.

ReservedEnumValue7: Not used.

ReservedEnumValue8: Not used.

ReservedEnumValue9: Not used.

ReservedEnumValue10: Not used.

ReservedEnumValue11: Not used.

AuthzContextInfoDeviceSids: Indicates the groups to which the device principal belongs and their attributes.

AuthzContextInfoUserClaims: Indicates the user's security attributes information.

AuthzContextInfoDeviceClaims: Indicates the device's security attributes information.

ReservedEnumValue15: Not used.

ReservedEnumValue16: Not used.

2.2.2.2 AUTHZ_SECURITY_ATTRIBUTE_OPERATION

The AUTHZ_SECURITY_ATTRIBUTE_OPERATION enumeration structure is used with the AuthzrModifyClaims operation (section [3.1.4.6](#)) to identify operation types on a client context object.

```
typedef enum _AUTHZ_SECURITY_ATTRIBUTE_OPERATION {
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_NONE = 0,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE_ALL = 1,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_ADD = 2,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_DELETE = 3,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE = 4
} AUTHZ_SECURITY_ATTRIBUTE_OPERATION;
```

AUTHZ_SECURITY_ATTRIBUTE_OPERATION_NONE: No operation will be performed.

AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE_ALL: The **ImpersonationAccessToken** on the specified client context will be replaced.

AUTHZ_SECURITY_ATTRIBUTE_OPERATION_ADD: A new claim will be added to the server's **ImpersonationAccessToken** associated with the specified client context.

AUTHZ_SECURITY_ATTRIBUTE_OPERATION_DELETE: An existing claim will be deleted from the **ImpersonationAccessToken** array associated with the specified client context if it is present in that array.

AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE: An existing claim will be replaced in the **ImpersonationAccessToken** array associated with the specified client context if it is present in the array.

2.2.2.3 AUTHZ_SID_OPERATION

The AUTHZ_SID_OPERATION enumeration indicates the type of SID operations that can be made by a call to the **AuthzrModifySids** operation (section [3.1.4.7](#)).

```
typedef enum _AUTHZ_SID_OPERATION {
    AUTHZ_SID_OPERATION_NONE = 0,
    AUTHZ_SID_OPERATION_REPLACE_ALL = 1,
    AUTHZ_SID_OPERATION_ADD = 2,
    AUTHZ_SID_OPERATION_DELETE = 3,
    AUTHZ_SID_OPERATION_REPLACE = 4
} AUTHZ_SID_OPERATION;
```

AUTHZ_SID_OPERATION_NONE: Do not modify anything.

AUTHZ_SID_OPERATION_REPLACE_ALL: Replace the existing SIDs with the specified SIDs. If replacement SIDs are not specified, delete the existing SIDs. This operation can be specified only once and must be the only operation specified.

AUTHZ_SID_OPERATION_ADD: Add a new SID. If the SID already exists, fail the call.

AUTHZ_SID_OPERATION_DELETE: Delete the specified SID. If the specified SID is not found, fail the call without taking action.

AUTHZ_SID_OPERATION_REPLACE: Replace the existing SID with the specified SID. If the SID does not exist, add the specified SID.

2.2.3 Structures

This protocol uses the following structures.

Structure name	Section	Description
AUTHZR_ACCESS_REPLY	2.2.3.1	Defines the contents of a remote access check reply.
AUTHZR_ACCESS_REQUEST	2.2.3.2	Defines the contents of a remote access check request.
AUTHZR_CONTEXT_INFORMATION	2.2.3.3	Contains security information about a principal.
AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE	2.2.3.4	Specifies a string value associated with a security attribute.
AUTHZR_SECURITY_ATTRIBUTE_V1	2.2.3.5	Specifies a security attribute and one or more value pairs.
AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE	2.2.3.6	Specifies a value associated with a security attribute.
AUTHZR_SECURITY_ATTRIBUTES_INFORMATION	2.2.3.7	Specifies one or more security attributes and values.
AUTHZR_SID_AND_ATTRIBUTES	2.2.3.8	Contains information about the security identifiers (SIDs) in a token.
AUTHZR_TOKEN_GROUPS	2.2.3.9	Represents a security identifier (SID) and its attributes.
AUTHZR_TOKEN_USER	2.2.3.10	Identifies the user associated with a token.
SR_SD	2.2.3.11	Contains a self-relative security descriptor.

2.2.3.1 AUTHZR_ACCESS_REPLY

The AUTHZR_ACCESS_REPLY structure defines the contents of a remote access check reply.

```
typedef struct _AUTHZR_ACCESS_REPLY {
    [range(0, 256)] DWORD ResultListLength;
    [size_is(ResultListLength)] ACCESS_MASK* GrantedAccessMask;
    [size_is(ResultListLength)] DWORD* Error;
} AUTHZR_ACCESS_REPLY;
```

ResultListLength: The number of elements in the *GrantedAccessMask* and *Error* arrays. This number matches the number of entries in the object type list structure used in the access check. The length MUST be between 1 and 256. If no object type is used to represent the object, *ResultListLength* MUST be set to 1.

GrantedAccessMask: A pointer to an array of granted access masks.

Error: A pointer to an array of DWORD error code results for each element of the array.

2.2.3.2 AUTHZR_ACCESS_REQUEST

The AUTHZR_ACCESS_REQUEST structure defines the contents of a remote access check request.

```
typedef struct _AUTHZR_ACCESS_REQUEST {
    ACCESS_MASK DesiredAccess;
    RPC_SID* PrincipalSelfSid;
    [range(0, 256)] DWORD ObjectTypeListLength;
    [size_is(ObjectTypeListLength)] OBJECT_TYPE_LIST* ObjectTypeList;
} AUTHZR_ACCESS_REQUEST;
```

DesiredAccess: The type of access to test.

PrincipalSelfSid: A pointer to the security identifier (SID) to use for the **principal self** SID in the **access control list (ACL)**.

ObjectTypeListLength: The number of elements in the *ObjectTypeList* array.

ObjectTypeList: A pointer to an array of OBJECT_TYPE_LIST structures in the object tree for the object.

2.2.3.3 AUTHZR_CONTEXT_INFORMATION

The AUTHZR_CONTEXT_INFORMATION structure contains security information about a principal.

```
typedef struct _AUTHZR_CONTEXT_INFORMATION {
    USHORT ValueType;
    [switch_is(ValueType)] union _AUTHZR_CONTEXT_INFORMATION_UNION {
        [case(0x1)]
            AUTHZR_TOKEN_USER* pTokenUser;
        [case(0x2, 0x3, 0xC)]
            AUTHZR_TOKEN_GROUPS* pTokenGroups;
        [case(0xD, 0xE)]
            AUTHZR_SECURITY_ATTRIBUTES_INFORMATION* pTokenClaims;
    } ContextInfoUnion;
} AUTHZR_CONTEXT_INFORMATION;
```

ValueType: Identifies the type of the ContextInfoUnion member.

Value	Meaning
0x0001 (user)	ContextInfoUnion contains an AUTHZR_TOKEN_USER structure, as specified in

Value	Meaning
	section 2.2.3.10 .
0x0002 (groups) 0x0003 (restricted groups) 0x000C (device groups)	ContextInfoUnion contains an AUTHZR_TOKEN_GROUPS structure, as specified in section 2.2.3.9 .
0x000D (user claim) 0x000E (device claim)	ContextInfoUnion contains an AUTHZR_SECURITY_ATTRIBUTES_INFORMATION structure, as specified in section 2.2.3.7 .

ContextInfoUnion: A pointer to an AUTHZR_TOKEN_USER, AUTHZR_TOKEN_GROUPS, or AUTHZR_SECURITY_ATTRIBUTES_INFORMATION structure, depending on the value of ValueType.

2.2.3.4 AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE

The AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE structure contains the string value of a claim.

```
typedef struct _AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE {
    [range(2, 32768)] ULONG Length;
    [string] [size_is(Length)] WCHAR* Value;
} AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE;
```

Length: The length of the string in the Value parameter.

Value: A Unicode string containing the pass-through string value of the claim.

2.2.3.5 AUTHZR_SECURITY_ATTRIBUTE_V1

The AUTHZR_SECURITY_ATTRIBUTE_V1 structure specifies one or more security attribute and value pairs that are associated with a remote authorization context.

```
typedef struct _AUTHZR_SECURITY_ATTRIBUTE_V1 {
    [range(2, 256)] ULONG Length;
    [string] [size_is(Length)] WCHAR* Value;
    USHORT ValueType;
    USHORT Reserved;
    ULONG Flags;
    [range(0, 1024)] ULONG ValueCount;
    [size_is(ValueCount)] AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE* Values;
} AUTHZR_SECURITY_ATTRIBUTE_V1;
```

Length: The length of the Value parameter, in bytes. MUST be between 2 and 256.

Value: A Unicode string containing the security value. This string MUST be between 2 and 256 bytes in length, inclusive.

ValueType: A union tag value indicating the type of information contained in **Values** member.

Reserved: Reserved. This member **MUST** be set to zero when sent and **MUST** be ignored when received.

Flags: **MUST** be zero or a combination of one or more of the following values.

Value	Description
AUTHZ_SECURITY_ATTRIBUTE_NON_INHERITABLE 0x00000001	This security attribute is not inherited across processes.
AUTHZ_SECURITY_ATTRIBUTE_VALUE_CASE_SENSITIVE 0x00000002	The value of the attribute is case sensitive. This flag is valid for values that contain string types.

ValueCount: The number of attribute and value pairs pointed to by the **Values** member. The number of attribute and value pairs **MUST** be between 0 and 1,024, inclusive.

Values: An array of AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE structures, as defined in section [2.2.3.6](#). Each structure contains a security attribute and value pair.

2.2.3.6 AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE

The AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE structure defines a claim.

```
typedef struct _AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE {
    USHORT ValueType;
    [switch_is(ValueType)] union _AUTHZR_SECURITY_ATTRIBUTE_UNION {
        [case(0x1)]
            LONG64 Int64;
        [case(0x2, 0x6)]
            ULONG64 UInt64;
        [case(0x3)]
            AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE String;
    } AttributeUnion;
} AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE;
```

ValueType: Identifies the type of the AttributeUnion member.

Value	Meaning
0x0001	AttributeUnion contains a LONG64 value.
0x0002, 0x0006	AttributeUnion contains a ULONG64 value.
0x0003	AttributeUnion contains an AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE structure, as specified in section 2.2.3.4 .

AttributeUnion: A LONG64, ULONG64, or AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE, depending on the value of ValueType.

2.2.3.7 AUTHZR_SECURITY_ATTRIBUTES_INFORMATION

The AUTHZR_SECURITY_ATTRIBUTES_INFORMATION structure specifies one or more security attributes.

```
typedef struct _AUTHZR_SECURITY_ATTRIBUTES_INFORMATION {
    USHORT Version;
    USHORT Reserved;
    [range(0, 1024)] ULONG AttributeCount;
    [size_is(AttributeCount)] AUTHZR_SECURITY_ATTRIBUTE_V1* Attributes;
} AUTHZR_SECURITY_ATTRIBUTES_INFORMATION;
```

Version: The version of this structure. This value MUST be set to 0x0001.

Reserved: Reserved. This member MUST be set to zero when sent and MUST be ignored when received.

AttributeCount: The number of attributes specified by the **Attribute** member. The number of attributes MUST be between zero and 1,024, inclusive.

Attributes: A pointer to an array of AUTHZR_SECURITY_ATTRIBUTE_V1 structures, defined in section [2.2.3.5](#).

2.2.3.8 AUTHZR_SID_AND_ATTRIBUTES

The AUTHZR_SID_AND_ATTRIBUTES structure contains information about the security identifiers (SIDs) in a token.

```
typedef struct _AUTHZR_SID_AND_ATTRIBUTES {
    RPC_SID* Sid;
    DWORD Attributes;
} AUTHZR_SID_AND_ATTRIBUTES;
```

Sid: A SID structure, as specified in [\[MS-DTYP\]](#) section 2.4.2.3. This is a pass-through value and SHOULD NOT be interpreted by the RAZA protocol.

Attributes: Specifies attributes associated with the SID. This is a pass-through value and SHOULD NOT be interpreted by the RAZA protocol.

2.2.3.9 AUTHZR_TOKEN_GROUPS

The AUTHZR_TOKEN_GROUPS structure represents a security identifier (SID) and its attributes.

```
typedef struct _AUTHZR_TOKEN_GROUPS {
    DWORD GroupCount;
    [size_is(GroupCount)] AUTHZR_SID_AND_ATTRIBUTES Groups[];
} AUTHZR_TOKEN_GROUPS;
```

GroupCount: Indicates the number of structures in the Groups array.

Groups: An array of AUTHZR_SID_AND_ATTRIBUTES structures (section [2.2.3.8](#)) representing groups associated with the token.

2.2.3.10 AUTHZR_TOKEN_USER

The AUTHZR_TOKEN_USER structure identifies the user associated with a token.

```
typedef struct _AUTHZR_TOKEN_USER {
    AUTHZR_SID_AND_ATTRIBUTES User;
} AUTHZR_TOKEN_USER;
```

User: Contains an AUTHZR_SID_AND_ATTRIBUTES structure (section [2.2.3.8](#)) representing the user associated with the access token.

2.2.3.11 SR_SD

The SR_SD structure defines a self-relative security descriptor. A self-relative security descriptor contains the security descriptor structure itself and the necessary security information associated with the descriptor.

```
typedef struct _SR_SD {
    [range(20, 131228)] DWORD dwLength;
    [size_is(dwLength)] BYTE* pSrSd;
} SR_SD;
```

dwLength: The length, in bytes, of the data pointed to in the **pSrSd** member.

pSrSd: A pointer to a self-relative security descriptor.

3 Protocol Details

The Remote Authorization Protocol is used to approximate an access control decision that would be made when a given principal attempts to access a hypothetical resource on a remote service that is protected with a given authorization policy.

All remote authorization methods return 0x00000000 on success; otherwise, they return a 32-bit, nonzero Win32 error code. For more details about Win32 error values, see [\[MS-ERREF\]](#).

Unless otherwise specified, the pointer type for the RAZA RPC interface is `pointer_default(unique)`. Method calls are received at a dynamically assigned endpoint ([\[MS-RPCE\]](#) section 2.1.1.1). The endpoints for the Netlogon service are negotiated by the RPC endpoint mapper ([\[MS-RPCE\]](#) section 2.1.1.1).

The client side of this protocol is simply a pass-through. That is, there are no additional timers or other states required on the client side of this protocol. Calls made by the higher-layer protocol or application are passed directly to the transport, and the results returned by the transport are passed directly back to the higher-layer protocol or application.

3.1 authzr Server Details

3.1.1 Abstract Data Model

This section describes a conceptual model of possible data organization that an implementation maintains to participate in this protocol. The organization is provided to explain how the protocol behaves. This document does not mandate that implementations adhere to this model as long as their external behavior is consistent with that specified in this document.

The RAZA server maintains one or more of the following abstract data types as abstract variables:

- **ImpersonationAccessToken (Public):** A Token/Authorization Context (see [\[MS-DTYP\]](#) section 2.5.2).
- **ClientContext:** A data structure containing the following members:
 - **RPCClient:** An AUTHZR_HANDLE structure (section [2.2.1.1](#)).
 - **AuthzContext:** An **ImpersonationAccessToken**.

Additionally, the RAZA server MUST maintain the following data structure:

- **ClientContextList:** A list of **ClientContext** objects.

3.1.2 Timers

None.

3.1.3 Initialization

The authzr server registers an endpoint with RPC over TCP/IP. The authzr server MUST register the Negotiate security support provider authentication_type constant [0x09] as the security provider ([\[MS-RPCE\]](#) section 3.3.3.1.3) used by the RPC interface.

The **ClientContextList** is emptied during initialization.

3.1.4 Message Processing Events and Sequencing Rules

This interface includes the following methods.

Method	Description
AuthzrFreeContext	Opnum: 0
AuthzrInitializeContextFromSid	Opnum: 1
AuthzrInitializeCompoundContext	Opnum: 2
AuthzrAccessCheck	Opnum: 3
AuthzGetInformationFromContext	Opnum: 4
AuthzrModifyClaims	Opnum: 5
AuthzrModifySids	Opnum: 6

All methods MUST NOT throw exceptions.

3.1.4.1 AuthzrFreeContext (Opnum 0)

The `AuthzrFreeContext` method (opnum 0) frees all remote structures and memory associated with the client context identified by the `ContextHandle` parameter.

```
DWORD AuthzrFreeContext(  
    [in, out] AUTHZR_HANDLE* ContextHandle);
```

ContextHandle: A pointer to an `AUTHZR_HANDLE` structure, as defined in section [2.2.1.1](#). This handle indicates the client context to be freed.

Return Values:

If the function succeeds, it MUST return `0x00000000`.

If the function fails, it MUST return a nonzero 32-bit error code.

When a remote authorization server receives this message, it MUST look up the **ClientContext** structure in the **ClientContextTable** ADM element and free all structures and memory associated with the **ClientContext**.

3.1.4.2 AuthzrInitializeContextFromSid (Opnum 1)

The `AuthzrInitializeContextFromSid` method (opnum 1) creates a client context from a given security identifier (SID). For domain SIDs, token group and claim attributes will be retrieved from **Active Directory** through Kerberos.

```
DWORD AuthzrInitializeContextFromSid(  
    [in] handle_t Binding,  
    [in] DWORD Flags,  
    [in] SID* Sid,  
    [in] [unique] LARGE_INTEGER* pExpirationTime,  
    [in] LUID Identifier,
```

```
[out] AUTHZR_HANDLE* ContextHandle);
```

Binding: A primitive RPC handle that identifies a particular client/server binding.

Flags: Indicates the type of logon behavior when initializing the client context. The following flags are defined.

Value	Description
0x00000000	When no flags are set, AuthzInitializeContextFromSid attempts to retrieve the user's token group information by performing an S4U logon.
AUTHZ_COMPUTE_PRIVILEGES (0x00000008)	AuthzInitializeContextFromSid retrieves privileges for the new context. If this function performs an S4U logon, it retrieves privileges from the token. Otherwise, it retrieves privileges from all SIDs in the context.

All other bits MUST be set to zero.

Sid: A pointer to the SID of the principal for whom a remote client context will be created. This MUST be a valid user or computer account.

pExpirationTime: Reserved. This parameter MUST be set to NULL when sent and MUST be ignored when received.

Identifier: Reserved. This parameter MUST be set to zero when sent and MUST be ignored when received.

ContextHandle: A pointer to an AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#).

Return Values:

If the function succeeds, the function MUST return 0x00000000.

If the function fails, it MUST return a nonzero error code.

When a RAZA server receives this message, the server MUST perform the following:

1. If any bits other than 0x00000008 are set in *Flags*, the server MUST return ERROR_INVALID_PARAMETER.
2. Call *LsarOpenPolicy* ([\[MS-LSAT\]](#) section 3.1.4.2) with the following as input:
 - *SystemName*: NULL.
 - *DesiredAccess*: Contains the bit value 0x00000800 for POLICY_LOOKUP_NAMES.
3. Call *LsarLookupSids* ([\[MS-LSAT\]](#) section 3.1.4.11) on the returned **PolicyHandle**.
 - *PolicyHandle*: The **PolicyHandle** returned from the aforementioned *LsarOpenPolicy*.
 - *SidEnumBuffer*: The **SidInfo** part of this structure contains the *Sid* parameter. The **Entries** part of this structure is set to 1. **LookupLevel** is set to *LsapLookupWksta*.

The return values from *LsarLookupSids* are as follows:

- **ReferencedDomains list:** The domain name is found as follows:
 1. Locate the entry in the **TranslatedNames** list that corresponds to the SID in question. This entry contains a **Names** structure with a **DomainIndex**.
 2. Find the **ReferencedDomains** list entry with an index that matches the **DomainIndex** from the structure in the preceding step. The domain name is found in the **Name** field of the **Domains** structure.
 - **TranslatedNames:** Contains the **UserName** in the **Name** field of the **Names** structure of the entry in the list corresponding to the SID in question (from the *SidEnumBuffer* input list).
4. Perform a Kerberos S4U2Self service ticket request using the S4U2self KRB_TGS_REQ/KRB_TGS_REP protocol extension as specified in [\[MS-SFU\]](#) section 3.1.5.1.1.1.
 - The *userName* MUST be set to the user name obtained in step 2.
 - The *userRealm* MUST be set to the domain name of the obtained in step 2.
 - The *chksum* MUST be set as specified in [\[MS-SFU\]](#) section 2.2.2.
 - The *auth-package* MUST be set to "Kerberos".
 5. Initialize and populate an **ImpersonationAccessToken** as specified in [\[MS-KILE\]](#) section 3.4.5.3.
 6. Allocate and initialize a new AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#), and assign **ContextHandle** to the new structure.
 7. Allocate memory for a new **ClientContext** object, set the **RPCClient** member to the AUTHZR_HANDLE initialized in step 6, and set **AuthzContext** to the **ImpersonationAccessToken** initialized in step 5.
 8. Append the **ClientContext** object created in step 7 to the **ClientContextList**.

3.1.4.3 AuthzrInitializeCompoundContext (Opnum 2)

The AuthzrInitializeCompoundContext method (opnum 2) creates a compound context from two specified context handles.

```
DWORD AuthzrInitializeCompoundContext(
    [in] AUTHZR_HANDLE UserContextHandle,
    [in] AUTHZR_HANDLE DeviceContextHandle,
    [out] AUTHZR_HANDLE* CompoundContextHandle);
```

UserContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#), that represents the user context for the compound context.

DeviceContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#), that represents the device context for the compound context.

CompoundContextHandle: A pointer to an AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#).

Return Values:

If the function succeeds, the function MUST return 0x00000000. If the function fails, it MUST return a nonzero value.

When a RAZA server receives this message, the server MUST perform the following:

1. Allocate a new **ImpersonationAccessToken**.
2. Copy the **ImpersonationAccessToken.Sids** array in the **ImpersonationAccessToken** of the **UserContextHandle** into the **ImpersonationAccessToken.Sids** array in the **ImpersonationAccessToken** created in step 1.
3. Copy the **ImpersonationAccessToken.UserIndex** field in the **ImpersonationAccessToken** of the **UserContextHandle** to the **ImpersonationAccessToken.UserIndex** field in the **ImpersonationAccessToken** created in step 1.
4. Copy the **ImpersonationAccessToken.UserClaims** array in the **ImpersonationAccessToken** of the **UserContextHandle** to the **ImpersonationAccessToken.UserClaims** array in the **ImpersonationAccessToken** created in step 1.
5. Copy the **ImpersonationAccessToken.Sids** array in the **ImpersonationAccessToken** of the *DeviceContextHandle* into the **ImpersonationAccessToken.DeviceSids** array in the **ImpersonationAccessToken** created in step 1.
6. Copy the **ImpersonationAccessToken.UserIndex** field in the **ImpersonationAccessToken** of the *DeviceContextHandle* to the **ImpersonationAccessToken.DeviceIndex** field in the **ImpersonationAccessToken** created in step 1.
7. Copy the **ImpersonationAccessToken.UserClaims** array in the **ImpersonationAccessToken** of the *DeviceContextHandle* to the **ImpersonationAccessToken.DeviceClaims** array in the **ImpersonationAccessToken** created in step 1.
8. Allocate and initialize a new AUTHZR_HANDLE structure.
9. Allocate a new **ClientContext** object, set the **RPCClient** member to the AUTHZR_HANDLE allocated in step 8, and set the **AuthzContext** member to the **ImpersonationAccessToken** created in step 1.
10. Add the new **ClientContext** object to the **ClientContextList**.

3.1.4.4 AuthzrAccessCheck (Opnum 3)

The AuthzrAccessCheck method (opnum 3) determines which access bits can be granted to a client for a given set of security descriptors. The AUTHZR_ACCESS_REPLY structure returns an array of granted access masks and error status.

```
DWORD AuthzrAccessCheck(  
    [in] AUTHZR_HANDLE ContextHandle,  
    [in] DWORD Flags,  
    [in] AUTHZR_ACCESS_REQUEST* pRequest,  
    [in] [range(1, 16)] DWORD SecurityDescriptorCount,  
    [in] [size_is(SecurityDescriptorCount)] SR_SD* pSecurityDescriptors,  
    [in, out] AUTHZR_ACCESS_REPLY* pReply);
```

ContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#), containing the client context handle.

Flags: Reserved. This parameter MUST be set to zero.

pRequest: A pointer to an AUTHZR_ACCESS_REQUEST structure, as defined in section [2.2.3.2](#). This structure contains the body of the "what-if" access check request.

SecurityDescriptorCount: The number of security descriptors in the *pSecurityDescriptors* parameter, not including the primary security descriptor.

pSecurityDescriptors: A pointer to an array of SR_SD structures, as defined in section [2.2.3.11](#). The first entry in this array is the primary security descriptor, and it will be used as the security descriptor for the AccessCheck evaluation.

pReply: A pointer to an AUTHZR_ACCESS_REPLY structure, as defined in section [2.2.3.1](#). This parameter will contain the body of the access check response.

Return Values:

If the function succeeds, the function MUST return 0x00000000.

If the function fails, it MUST return a nonzero error code.

When a RAZA server receives this message, the server MUST perform the following:

- Check that the upper 16 bits of the **Flags** parameter are set to zero, and if not, return a nonzero error code.
- If the client connects to the server using ObjectUUID as 5fc860e0-6f6e-4fc2-83cd-46324f25e90b then remove all ACEs of type SYSTEM_SCOPED_POLICY_ID_ACE ([\[MS-DTYP\]](#) section 2.4.4.16) from the *pSecurityDescriptors[0]* parameter.
- Perform an AccessCheck evaluation using the algorithm specified in [\[MS-DTYP\]](#) section 2.5.3.2, where the preceding parameters are mapped to the parameter names of the algorithm described according to the following table.

AccessCheck pseudocode parameter	RAZA protocol AuthzrAccessCheck evaluation
<i>SecurityDescriptor</i>	<i>pSecurityDescriptors[0]</i>
<i>Token (Authorization Context)</i>	The ImpersonationAccessToken in the ClientContext object associated with the <i>ContextHandle</i>
<i>Access Request mask</i>	The DesiredAccess member of the AUTHZR_ACCESS_REQUEST structure pointed to by <i>pRequest</i>
<i>Object Tree</i>	The ObjectTypeList member of the AUTHZR_ACCESS_REQUEST structure pointed to by <i>pRequest</i>
<i>PrincipalSelfSubst SID</i>	The PrincipalSelfSid member of the AUTHZR_ACCESS_REQUEST structure pointed to by <i>pRequest</i>
<i>GrantedAccess</i>	The memory location of the GrantedAccessMask member of the AUTHZR_ACCESS_REPLY structure pointed to by <i>pRequest</i>

3.1.4.5 AuthzGetInformationFromContext (Opnum 4)

The AuthzGetInformationFromContext method (opnum 4) returns information about the identified client context.


```
DWORD AuthzGetInformationFromContext(  
    [in] AUTHZR_HANDLE ContextHandle,  
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS InfoClass,  
    [out] AUTHZR_CONTEXT_INFORMATION** ppContextInformation);
```

ContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#). Represents the client context to retrieve information from.

InfoClass: An AUTHZ_CONTEXT_INFORMATION_CLASS enumeration, as defined in section [2.2.2.1](#). Possible values for this field are specified in section [2.2.2.1](#).

ppContextInformation: A two-layer pointer to an AUTHZR_CONTEXT_INFORMATION structure, as defined in section [2.2.3.3](#). Used to return the context information.

Return Values:

If the function succeeds, the function MUST return 0x00000000.

If the function fails, it MUST return a nonzero error code value.

When a RAZA server receives this message, the server MUST perform the following:

- If the *InfoClass* parameter is one of the following values, the RAZA server MUST:
 1. Initialize a new AUTHZR_CONTEXT_INFORMATION structure.
 2. Set the *ppContextInformation* parameter to the memory address of the new structure.
 3. Perform the corresponding action using the **ImpersonationAccessToken** in the **ClientContext** object identified in the *ContextHandle* parameter:
 - **AuthzContextInfoUserSid** (1):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 1.
 2. Set the **pTokenUser** member of the new AUTHZR_CONTEXT_INFORMATION object to the address of the element at the **ImpersonationAccessToken.UserIndex** of the **ImpersonationAccessToken.Sids** array.
 - **AuthzContextInfoGroupsSids** (2):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 2.
 2. Set the **pTokenGroups** member of the new AUTHZR_CONTEXT_INFORMATION object to the value of the **ImpersonationAccessToken.Sids** member.
 - **AuthzContextInfoRestrictedSids** (3):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 3.
 2. Set the **pTokenGroups** member of the new AUTHZR_CONTEXT_INFORMATION object to the value of the **ImpersonationAccessToken.RestrictedSids** member.
 - **AuthzContextInfoDeviceSids** (12):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 12.

2. Set the **pTokenGroups** member of the new AUTHZR_CONTEXT_INFORMATION object to the value of the **ImpersonationAccessToken.DeviceSids** member.
- **AuthzContextInfoUserClaims** (13):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 13.
 2. Set the **pTokenClaims** member of the new AUTHZR_CONTEXT_INFORMATION object to the value of the **ImpersonationAccessToken.Claims** member.
 - **AuthzContextInfoDeviceClaims** (14):
 1. Set the **ValueType** member in the new AUTHZR_CONTEXT_INFORMATION object to 14.
 2. Set the **pTokenClaims** member of the new AUTHZR_CONTEXT_INFORMATION object to the value of the **ImpersonationAccessToken.DeviceClaims** member.
 - If the *InfoClass* parameter is any other value, the requested information is not supported. The RAZA server MUST set *ppContextInformation* to NULL and return a nonzero error code value.

3.1.4.6 AuthzModifyClaims (Opnum 5)

The AuthzModifyClaims method (opnum 5) modifies information about the identified client context.

```
DWORD AuthzModifyClaims (
    [in] AUTHZR_HANDLE ContextHandle,
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS ClaimClass,
    [in] [range(1, 65535)] DWORD OperationCount,
    [in] [size_is(OperationCount)] AUTHZ_SECURITY_ATTRIBUTE_OPERATION* pClaimOperations,
    [in] [unique] AUTHZR_SECURITY_ATTRIBUTES_INFORMATION* pClaims);
```

ContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#). Represents the client context to modify.

ClaimClass: An AUTHZ_CONTEXT_INFORMATION_CLASS enumeration, as defined in section [2.2.2.1](#). Indicates the claim class.

OperationCount: The number of operations to be performed.

pClaimOperations: A pointer to an array of AUTHZ_SECURITY_ATTRIBUTE_OPERATION enumerations, as defined in section [2.2.2.2](#). Specifies the operations to be performed on each claim.

pClaims: A pointer to an array of AUTHZR_SECURITY_ATTRIBUTES_INFORMATION structures, as defined in section [2.2.3.7](#). Contains the claim(s) used to modify the client context.

Return Values:

If the function succeeds, the function MUST return 0x00000000.

If the function fails, it MUST return a nonzero error code value.

When a RAZA server receives this message, the server MUST perform the following:

If the *InfoClass* parameter is any value other than AuthzContextInfoUserClaims (13) or AuthzContextInfoDeviceClaims (14), the requested modification is not supported. When this happens, the RAZA server MUST set *ppContextInformation* to NULL and return FALSE.

The RAZA server MUST check the first element in the *pClaimOperations* array as indicated by *OperationCount* and perform operations as follows:

- If the value pointed to by the *pClaimOperations* parameter is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_NONE**, the RAZA server MUST return 0x00000000.
- If the value pointed to by the *pClaimsOperations* parameter is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE_ALL**, the RAZA server MUST perform the following on the **ImpersonationAccessToken** in the **ClientContext** identified by the *ContextHandle*:
 1. Map the *InfoClass* parameter value to the corresponding **ImpersonationAccessToken** array according to the following table and replace it with the *pClaims Attribute* member array.
 2. Return 0x00000000 if the operation was a success; otherwise, return a nonzero error code.
- If the value pointed to by the *pClaimOperations* parameter is any other value of **AUTHZ_SECURITY_ATTRIBUTE_OPERATION**, perform the steps prescribed after the next paragraph.

The RAZA server MUST perform the following steps on each element in the *pClaimOperations* array as indicated by *OperationCount*:

1. If the element is not the first element and the value is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_NONE** or **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE_ALL**, the RAZA server MUST return a nonzero error code. The case in which the first element is one of these values is described above.
2. If the element is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_ADD**, append the corresponding element in the *pClaims Attributes* array to the **ImpersonationAccessToken** array identified according to the following table.
3. If the element is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_DELETE**, search the **ImpersonationAccessToken** array identified according to the following table for a member whose **Value** member equals the **Value** member of the corresponding element of the **Attributes** array in the *pClaims* parameter. If one is found, delete that element from the identified **ImpersonationAccessToken** array and free any memory associated with that element.
4. If the element is **AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE**, search the **ImpersonationAccessToken** array identified according to the following table for a member whose **Value** member equals the **Value** member of the corresponding element of the **Attributes** array in the *pClaims* parameter.
 1. If the attribute is located, replace the **Values** member of the located attribute with the replacement **Values** member, which is located in the corresponding **Attributes** array element in the **Attributes** member of *pClaims*. If the replacement **Values** member does not exist, the located attribute is deleted.
 2. If the attribute is not located, it is added using the replacement **Values** member, which is located in the corresponding **Attributes** array element in the **Attributes** member of *pClaims*. If the replacement **Values** member does not exist, the operation is ignored and no failure is reported.

ClaimClass parameter value	Corresponding ImpersonationAccessToken array
<i>AuthzContextInfoUserClaims</i>	ImpersonationAccessToken.Claims
<i>AuthzContextInfoDeviceClaims</i>	ImpersonationAccessToken.DeviceClaims

3.1.4.7 AuthzrModifySids (Opnum 6)

The AuthzrModifySids method (opnum 6) modifies the list of SIDs associated with the identified client context.

```
DWORD AuthzrModifySids (
    [in] AUTHZR_HANDLE ContextHandle,
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS SidClass,
    [in] [range(1, 65535)] DWORD OperationCount,
    [in] [size_is(OperationCount)] AUTHZ_SID_OPERATION* pSidOperations,
    [in] [unique] AUTHZR_TOKEN_GROUPS* pSids);
```

ContextHandle: An AUTHZR_HANDLE structure, as defined in section [2.2.1.1](#), representing the client context to be modified.

SidClass: An AUTHZ_CONTEXT_INFORMATION_CLASS enumeration value, as defined in section [2.2.2.1](#), indicating the SID class.

OperationCount: The number of operations to be performed.

pSidOperations: A pointer to an array of AUTHZ_SID_OPERATION enumeration values that specify the group modifications to be made.

pSids: A pointer to an AUTHZR_TOKEN_GROUPS structure, as defined in section [2.2.3.9](#), specifying the groups to be modified.

Return Values:

If the function succeeds, it MUST return 0x00000000.

If the function fails, it MUST return a nonzero error code value.

On receipt of this message, a RAZA server MUST complete the following process:

1. If the InfoClass parameter contains any value other than AuthzContextInfoGroupSids (2) or AuthzContextInfoDeviceSids (12), or if the requested modification is not supported, the RAZA server MUST return ERROR_INVALID_PARAMETER.
2. The RAZA server MUST check the first element in the pSidOperations array as indicated by OperationCount.
3. If the value pointed to by the pSidOperations parameter is AUTHZ_SID_OPERATION_NONE, the RAZA server must return 0x00000000.
4. If the value pointed to by the pSidOperations parameter is AUTHZ_SID_OPERATION_REPLACE_ALL, the RAZA server MUST perform the following operations on the ImpersonationAccessToken in the ClientContext identified by the ContextHandle:

1. Map the InfoClass parameter value to the corresponding ImpersonationAccessToken array according to the following table, and replace it with the pSids Groups member array.
2. Return 0x00000000 if the operation is successful; otherwise, return a nonzero error code.
5. If the value pointed to by the pSidOperations parameter is any other value of the **AUTHZ_SID_OPERATION** enumeration, continue with the following process.

The RAZA server MUST complete the following process for each element in the pSidOperations array as indicated by OperationCount:

1. If the element is not the first element and the value is AUTHZ_SID_OPERATION_NONE or AUTHZ_SID_OPERATION_REPLACE_ALL, the RAZA server MUST return a nonzero error code. The case in which the first element is one of these values is described earlier.
2. If the element is **AUTHZ_SID_OPERATION_ADD**, search the **ImpersonationAccessToken** array identified according to the following table for a member whose member equals the member of the corresponding element of the **Groups** array in the pSids parameter. If one is found, the RAZA server MUST return ERROR_GROUP_EXISTS, otherwise, append the corresponding element in the **Groups** array in the pSids parameter to the **ImpersonationAccessToken** array identified according to the following table. If the corresponding element of the **Groups** array in the pSids parameter does not exist, then RAZA server MUST fail with ERROR_INVALID_PARAMETER.
3. If the element is AUTHZ_SID_OPERATION_DELETE, search the **ImpersonationAccessToken** array that is identified according to the following table for a member whose member equals the member of the corresponding element of the Groups array in the pSids parameter. If one is found, delete that element from the identified **ImpersonationAccessToken** array and free any memory that was associated with that element. If the search fails, the RAZA server MUST return ERROR_NOT_FOUND. If the corresponding element of the **Groups** array in the pSids parameter does not exist, then the RAZA server MUST fail with ERROR_INVALID_PARAMETER.
4. If the element is AUTHZ_SID_OPERATION_REPLACE, search the ImpersonationAccessToken array identified according to the following table for a member whose member equals the member of the corresponding element of the Groups array in the pSids parameter.
 1. If the Sid is located, replace the member of the Sid located in the array with the replacement Sid, which is located in the corresponding Groups array element in the Groups member of the pSids parameter. If the corresponding replacement **Groups** member does not exist, then the RAZA server MUST fail with ERROR_INVALID_PARAMETER.
 2. If the Sid is not located, it is added using the replacement Sid, which is located in the corresponding Groups array element in the Groups member of the pSids parameter. If the corresponding replacement **Groups** member does not exist, then the RAZA server MUST fail with ERROR_INVALID_PARAMETER.

SIDClass parameter value	Corresponding ImpersonationAccessToken array
AuthzContextInfoGroupSids	ImpersonationAccessToken.Sids
AuthzContextInfoDeviceSids	ImpersonationAccessToken.DeviceSids

3.1.5 Timer Events

None.

3.1.6 Other Local Events

None.

4 Protocol Examples

The following example shows a sample call sequence from a client to a server for a typical use of the RAZA protocol to query the permissions available to a given user with the SID S-1-5-21-3448151421-356457007-600757626-4138921 for a resource protected on the server with a security descriptor where built-in administrators and local system have file all access, everyone has read and execute, and the user has read, write, and execute.

- Client sends AuthzrInitializeContextFromSid.

Parameter field	Parameter value
<i>Handle_t</i>	[RPC handle to server]
<i>Flags</i>	0x8
<i>SID</i>	S-1-5-21-3448151421-356457007-600757626-4138921
<i>pExpirationTime</i>	NULL
<i>LUID</i>	{0xdead,0xbeef}

- Client receives AuthzrInitializeContextFromSid.

Parameter field	Parameter value
<i>Status</i>	0
<i>ContextHandle</i>	[context handle](This data is opaque to the client.)

- Client sends AuthzrAccessCheck.

Parameter field	Parameter value
<i>Handle_t</i>	[RPC handle to server]

Parameter field	Parameter value
<i>ContextHandle</i>	[ContextHandle received from server using AuthzrInitializeContextFromSid]
<i>Flags</i>	0x0
<i>pRequest.DesiredAccess</i>	0x02000000 (MAXIMUM_ALLOWED)
<i>pRequest.PrincipalSelfSid</i>	NULL
<i>pRequest.ObjectTypeListLength</i>	0
<i>pRequest.ObjectTypeList</i>	NULL
<i>SecurityDescriptorCount</i>	1
<i>pSecurityDescriptors</i>	<pre> 01 00 04 80 14 00 00 00 24 00 00 00 00 00 00 00 30 00 00 00 01 02 00 00 00 00 00 05 20 00 00 00 20 02 00 00 01 01 00 00 00 00 00 05 12 00 00 00 02 00 6C 00 04 00 00 00 00 00 18 00 FF 01 1F 00 01 02 00 00 00 00 00 05 20 00 00 00 20 02 00 00 00 00 14 00 FF 01 1F 00 01 01 00 00 00 00 00 05 12 00 00 00 00 00 14 00 A9 00 12 00 01 01 00 00 00 00 00 01 00 00 00 00 00 00 24 00 BF 01 12 00 01 05 00 00 00 00 00 05 15 00 00 00 7D 9D 86 CD 2F 1A 3F 15 7A D5 CE 23 A9 27 3F 00 </pre> <p>This is equivalent to the following string value: O:BAG:SYD:(A;;FA;;;BA)(A;;FA;;;SY)(A;;FRFX;;;WD)(A;;FWFRFX;;;S-1-5-21-3448151421-356457007-600757626-4138921)</p>

- Client receives AuthzrAccessCheck.

Parameter field	Parameter value
<i>Status</i>	0
<i>pReply.ResultListLength</i>	1
<i>pReply.GrantedAccessMask</i>	0x1201BF (FILE_GENERIC_READ FILE_GENERIC_WRITE FILE_GENERIC_EXECUTE)
<i>pReply.Error</i>	ERROR_SUCCESS

- Client sends AuthzrFreeContext.

Parameter field	Parameter value
<i>Handle_t</i>	[RPC handle to server]
<i>ContextHandle</i>	[ContextHandle received from server using AuthzrInitializeContextFromSid]

- Client receives AuthzrFreeContext.

Parameter field	Parameter value
<i>Status</i>	0
<i>ContextHandle</i>	NULL

5 Security

5.1 Security Considerations for Implementers

Use of the RAZA protocol requires the client user to have access to read the user and claim information of security principals that the client is performing authorization queries on. [<2>](#) Access to the RAZA interface should be limited to a subset of the principals who have access to read account information.

5.2 Index of Security Parameters

None.

6 Appendix A: Full IDL

For ease of implementation, the full IDL is provided below, where "ms-dtyp.idl" refers to the IDL found in [\[MS-DTYP\]](#) Appendix A. The syntax uses the IDL syntax extensions defined in [\[MS-RPCE\]](#) sections [2.2.4](#) and [3.1.1.5.1](#). For example, as noted in [\[MS-RPCE\]](#) section 2.2.4.9, a pointer_default declaration is not required and pointer_default(unique) is assumed.

```
import "ms-dtyp.idl";

[uuid(0b1c2170-5732-4e0e-8cd3-d9b16f3b84d7)]
[version(0.0)]
[pointer_default(ptr)]
[ms_union]
interface authzr {
    typedef [context_handle] PVOID AUTHZR_HANDLE;
    typedef struct _AUTHZR_ACCESS_REQUEST {
        ACCESS_MASK DesiredAccess;
        RPC_SID * PrincipalSelfSid;
        [range(0,256)] DWORD ObjectTypeListLength;
        [size_is(ObjectTypeListLength)] OBJECT_TYPE_LIST * ObjectTypeList;
    } AUTHZR_ACCESS_REQUEST;

    typedef struct _SR_SD {
        [range(20,131228)] DWORD dwLength;
        [size_is(dwLength)] BYTE * pSrSd;
    } SR_SD;

    typedef struct _AUTHZR_ACCESS_REPLY {
        [range(0,256)] DWORD ResultListLength;
        [size_is(ResultListLength)] ACCESS_MASK * GrantedAccessMask;
        [size_is(ResultListLength)] DWORD * Error;
    } AUTHZR_ACCESS_REPLY;

    typedef enum _AUTHZ_CONTEXT_INFORMATION_CLASS {
        AuthzContextInfoUserSid = 1,
        AuthzContextInfoGroupsSids = 2,
        AuthzContextInfoRestrictedSids = 3,
        ReservedEnumValue4 = 4,
        ReservedEnumValue5 = 5,
        ReservedEnumValue6 = 6,
        ReservedEnumValue7 = 7,
        ReservedEnumValue8 = 8,
        ReservedEnumValue9 = 9,
        ReservedEnumValue10 = 10,
        ReservedEnumValue11 = 11,
        AuthzContextInfoDeviceSids = 12,
        AuthzContextInfoUserClaims = 13,
        AuthzContextInfoDeviceClaims = 14,
        ReservedEnumValue15 = 15,
        ReservedEnumValue16 = 16
    } AUTHZ_CONTEXT_INFORMATION_CLASS;

    typedef struct _AUTHZR_SID_AND_ATTRIBUTES {
        RPC_SID * Sid;
        DWORD Attributes;
    } AUTHZR_SID_AND_ATTRIBUTES;

    typedef struct _AUTHZR_TOKEN_USER {
```

```

    AUTHZR_SID_AND_ATTRIBUTES User;
} AUTHZR_TOKEN_USER;

typedef struct _AUTHZR_TOKEN_GROUPS {
    DWORD GroupCount;
    [size_is(GroupCount)] AUTHZR_SID_AND_ATTRIBUTES Groups[];
} AUTHZR_TOKEN_GROUPS;

typedef struct _AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE {
    [range(2,32768)] ULONG Length;
    [string] [size_is(Length)] WCHAR * Value;
} AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE;

typedef struct _AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE {
    USHORT ValueType;
    [switch_is(ValueType)] union AUTHZR_SECURITY_ATTRIBUTE_UNION {
        [case(0x1)]
            LONG64 Int64;
        [case(0x2, 0x6)]
            ULONG64 UInt64;
        [case(0x3)]
            AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE String;
    } AttributeUnion;
} AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE;

typedef struct _AUTHZR_SECURITY_ATTRIBUTE_V1 {
    [range(2,256)] ULONG Length;
    [string] [size_is(Length)] WCHAR * Value;
    USHORT ValueType;
    USHORT Reserved;
    ULONG Flags;
    [range(0,1024)] ULONG ValueCount;
    [size_is(ValueCount)] AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE * Values;
} AUTHZR_SECURITY_ATTRIBUTE_V1;

typedef struct _AUTHZR_SECURITY_ATTRIBUTES_INFORMATION {
    USHORT Version;
    USHORT Reserved;
    [range(0,1024)] ULONG AttributeCount;
    [size_is(AttributeCount)] AUTHZR_SECURITY_ATTRIBUTE_V1 * Attributes;
} AUTHZR_SECURITY_ATTRIBUTES_INFORMATION;

typedef struct _AUTHZR_CONTEXT_INFORMATION {
    USHORT ValueType;
    [switch_is(ValueType)] union AUTHZR_CONTEXT_INFORMATION_UNION {
        [case(0x1)]
            AUTHZR_TOKEN_USER * pTokenUser;
        [case(0x2, 0x3, 0xC)]
            AUTHZR_TOKEN_GROUPS * pTokenGroups;
        [case(0xD, 0xE)]
            AUTHZR_SECURITY_ATTRIBUTES_INFORMATION * pTokenClaims;
    } ContextInfoUnion;
} AUTHZR_CONTEXT_INFORMATION;

typedef enum _AUTHZ_SECURITY_ATTRIBUTE_OPERATION {
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_NONE = 0,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE_ALL = 1,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_ADD = 2,
    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_DELETE = 3,

```

```

    AUTHZ_SECURITY_ATTRIBUTE_OPERATION_REPLACE = 4
} AUTHZ_SECURITY_ATTRIBUTE_OPERATION;

typedef enum _AUTHZ_SID_OPERATION {
    AUTHZ_SID_OPERATION_NONE = 0,
    AUTHZ_SID_OPERATION_REPLACE_ALL = 1,
    AUTHZ_SID_OPERATION_ADD = 2,
    AUTHZ_SID_OPERATION_DELETE = 3,
    AUTHZ_SID_OPERATION_REPLACE = 4
} AUTHZ_SID_OPERATION;

DWORD AuthzrFreeContext(
    [in, out] AUTHZR_HANDLE * ContextHandle);
DWORD AuthzrInitializeContextFromSid(
    [in] handle_t Binding,
    [in] DWORD Flags,
    [in] RPC_SID * Sid,
    [in] [unique] LARGE_INTEGER * pExpirationTime,
    [in] LUID Identifier,
    [out] AUTHZR_HANDLE * ContextHandle);
DWORD AuthzrInitializeCompoundContext(
    [in] AUTHZR_HANDLE UserContextHandle,
    [in] AUTHZR_HANDLE DeviceContextHandle,
    [out] AUTHZR_HANDLE * CompoundContextHandle);
DWORD AuthzrAccessCheck(
    [in] AUTHZR_HANDLE ContextHandle,
    [in] DWORD Flags,
    [in] AUTHZR_ACCESS_REQUEST * pRequest,
    [in] [range(1,16)] DWORD SecurityDescriptorCount,
    [in] [size_is(SecurityDescriptorCount)] SR_SD * pSecurityDescriptors,
    [in, out] AUTHZR_ACCESS_REPLY * pReply);
DWORD AuthzGetInformationFromContext(
    [in] AUTHZR_HANDLE ContextHandle,
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS InfoClass,
    [out] AUTHZR_CONTEXT_INFORMATION ** ppContextInformation);
DWORD AuthzrModifyClaims(
    [in] AUTHZR_HANDLE ContextHandle,
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS ClaimClass,
    [in] [range(1,65535)] DWORD OperationCount,
    [in] [size_is(OperationCount)] AUTHZ_SECURITY_ATTRIBUTE_OPERATION * pClaimOperations,
    [in] [unique] AUTHZR_SECURITY_ATTRIBUTES_INFORMATION * pClaims);
DWORD AuthzrModifySids(
    [in] AUTHZR_HANDLE ContextHandle,
    [in] AUTHZ_CONTEXT_INFORMATION_CLASS SidClass,
    [in] [range(1,65535)] DWORD OperationCount,
    [in] [size_is(OperationCount)] AUTHZ_SID_OPERATION * pSidOperations,
    [in] [unique] AUTHZR_TOKEN_GROUPS * pSids);
};

```

7 Appendix B: Product Behavior

The information in this specification is applicable to the following Microsoft products or supplemental software. References to product versions include released service packs:

- Windows 8 operating system
- Windows Server 2012 operating system
- Windows 8.1 operating system
- Windows Server 2012 R2 operating system

Exceptions, if any, are noted below. If a service pack or Quick Fix Engineering (QFE) number appears with the product version, behavior changed in that service pack or QFE. The new behavior also applies to subsequent service packs of the product unless otherwise specified. If a product edition appears with the product version, behavior is different in that product edition.

Unless otherwise specified, any statement of optional behavior in this specification that is prescribed using the terms SHOULD or SHOULD NOT implies product behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that the product does not follow the prescription.

[<1> Section 1.3:](#) The RAZA client role is implemented on all Windows 8 and Windows 8.1 operating system-based products configured to run in a Windows domain environment. The RAZA server role is implemented on Windows Server 2012 and Windows Server 2012 R2 and is operating when the Windows Server 2012 or Windows Server 2012 R2 server is configured to run in a Windows domain environment.

[<2> Section 5.1:](#) In Windows, this access is controlled by membership in the Windows Authorization Access Group.

8 Change Tracking

This section identifies changes that were made to the [MS-RAA] protocol document between the November 2013 and February 2014 releases. Changes are classified as New, Major, Minor, Editorial, or No change.

The revision class **New** means that a new document is being released.

The revision class **Major** means that the technical content in the document was significantly revised. Major changes affect protocol interoperability or implementation. Examples of major changes are:

- A document revision that incorporates changes to interoperability requirements or functionality.
- The removal of a document from the documentation set.

The revision class **Minor** means that the meaning of the technical content was clarified. Minor changes do not affect protocol interoperability or implementation. Examples of minor changes are updates to clarify ambiguity at the sentence, paragraph, or table level.

The revision class **Editorial** means that the formatting in the technical content was changed. Editorial changes apply to grammatical, formatting, and style issues.

The revision class **No change** means that no new technical changes were introduced. Minor editorial and formatting changes may have been made, but the technical content of the document is identical to the last released version.

Major and minor changes can be described further using the following change types:

- New content added.
- Content updated.
- Content removed.
- New product behavior note added.
- Product behavior note updated.
- Product behavior note removed.
- New protocol syntax added.
- Protocol syntax updated.
- Protocol syntax removed.
- New content added due to protocol revision.
- Content updated due to protocol revision.
- Content removed due to protocol revision.
- New protocol syntax added due to protocol revision.
- Protocol syntax updated due to protocol revision.
- Protocol syntax removed due to protocol revision.

- Obsolete document removed.

Editorial changes are always classified with the change type **Editorially updated**.

Some important terms used in the change type descriptions are defined as follows:

- **Protocol syntax** refers to data elements (such as packets, structures, enumerations, and methods) as well as interfaces.
- **Protocol revision** refers to changes made to a protocol that affect the bits that are sent over the wire.

The changes made to this document are listed in the following table. For more information, please contact dochelp@microsoft.com.

Section	Tracking number (if applicable) and description	Major change (Y or N)	Change type
3.1.4.3 AuthzrInitializeCompoundContext (Opnum 2)	70819 Updated the steps the server takes after a RAZA server receives the message.	Y	Content updated.
3.1.4.4 AuthzrAccessCheck (Opnum 3)	70820 Changed Flags to be a reserved parameter that must be set to 0.	Y	Content updated.

9 Index

A

- Abstract data model
 - server
 - [authz](#) 19
 - [Applicability](#) 7
 - [AUTHZ_CONTEXT_INFORMATION_CLASSEnumeration](#) 10
 - [AUTHZ_SECURITY_ATTRIBUTE_OPERATIONEnumeration](#) 12
 - [AUTHZ_SID_OPERATIONEnumeration](#) 12
 - [AuthzGetInformationFromContext \(Opnum 4\) method](#) 24
 - [AUTHZR_ACCESS_REPLYstructure](#) 13
 - [AUTHZR_ACCESS_REQUESTstructure](#) 14
 - [AUTHZR_CONTEXT_INFORMATIONstructure](#) 14
 - [AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUEstructure](#) 15
 - [AUTHZR_SECURITY_ATTRIBUTE_V1_VALUEstructure](#) 16
 - [AUTHZR_SECURITY_ATTRIBUTE_V1structure](#) 15
 - [AUTHZR_SECURITY_ATTRIBUTES_INFORMATIONstructure](#) 17
 - [AUTHZR_SID_AND_ATTRIBUTESstructure](#) 17
 - [AUTHZR_TOKEN_GROUPSstructure](#) 17
 - [AUTHZR_TOKEN_USERstructure](#) 18
 - [AuthzAccessCheck \(Opnum 3\) method](#) 23
 - [AuthzFreeContext \(Opnum 0\) method](#) 20
 - [AuthzInitializeCompoundContext \(Opnum 2\) method](#) 22
 - [AuthzInitializeContextFromSid \(Opnum 1\) method](#) 20
 - [AuthzModifyClaims \(Opnum 5\) method](#) 26
 - [AuthzModifySids \(Opnum 6\) method](#) 28

C

- [Capability negotiation](#) 7
- [Change tracking](#) 39
- [Common data types](#) 9
 - [enumerations](#) 10
 - [structures](#) 13

D

- Data model - abstract
 - server
 - [authz](#) 19
- Data types
 - [common - overview](#) 9

E

- Enumerations
 - [AUTHZ_CONTEXT_INFORMATION_CLASS](#) 10
 - [AUTHZ_SECURITY_ATTRIBUTE_OPERATION](#) 12
 - [AUTHZ_SID_OPERATION](#) 12
 - [overview](#) 10

- Events
 - local
 - server
 - [authz](#) 30
 - timer
 - server
 - [authz](#) 29
- Examples
 - [overview](#) 31

F

- [Fields - vendor extensible](#) 8
- [Full IDL](#) 35

G

- [Glossary](#) 5

I

- [IDL](#) 35
- [Implementer - security considerations](#) 34
- [Index of security parameters](#) 34
- [Informative references](#) 6
- Initialization
 - server
 - [authz](#) 19
- [Introduction](#) 5

L

- Local events
 - server
 - [authz](#) 30

M

- Message processing
 - server
 - [authz](#) 20
- Messages
 - [common data types](#) 9
 - [transport](#) 9
- Methods
 - [AuthzGetInformationFromContext \(Opnum 4\)](#) 24
 - [AuthzAccessCheck \(Opnum 3\)](#) 23
 - [AuthzFreeContext \(Opnum 0\)](#) 20
 - [AuthzInitializeCompoundContext \(Opnum 2\)](#) 22
 - [AuthzInitializeContextFromSid \(Opnum 1\)](#) 20
 - [AuthzModifyClaims \(Opnum 5\)](#) 26
 - [AuthzModifySids \(Opnum 6\)](#) 28

N

- [Normative references](#) 6

O

[Overview \(synopsis\)](#) 6

P

[Parameters - security index](#) 34

[Preconditions](#) 7

[Prerequisites](#) 7

[Product behavior](#) 38

R

References

[informative](#) 6

[normative](#) 6

[Relationship to other protocols](#) 7

S

Security

[implementer considerations](#) 34

[parameter index](#) 34

Sequencing rules

[authzr](#) 20

Server

authzr

[abstract data model](#) 19

[AuthzrGetInformationFromContext \(Opnum 4\)](#)
method 24

[AuthzrAccessCheck \(Opnum 3\) method](#) 23

[AuthzrFreeContext \(Opnum 0\) method](#) 20

[AuthzrInitializeCompoundContext \(Opnum 2\)](#)
method 22

[AuthzrInitializeContextFromSid \(Opnum 1\)](#)

method 20

[AuthzrModifyClaims \(Opnum 5\) method](#) 26

[AuthzrModifySids \(Opnum 6\) method](#) 28

[initialization](#) 19

[local events](#) 30

[message processing](#) 20

[sequencing rules](#) 20

[timer events](#) 29

[timers](#) 19

[SR_SDstructure](#) 18

[Standards assignments](#) 8

Structures

[AUTHZR_ACCESS_REPLY](#) 13

[AUTHZR_ACCESS_REQUEST](#) 14

[AUTHZR_CONTEXT_INFORMATION](#) 14

[AUTHZR_SECURITY_ATTRIBUTE_STRING_VALUE](#)
15

[AUTHZR_SECURITY_ATTRIBUTE_V1](#) 15

[AUTHZR_SECURITY_ATTRIBUTE_V1_VALUE](#) 16

[AUTHZR_SECURITY_ATTRIBUTES_INFORMATION](#)
17

[AUTHZR_SID_AND_ATTRIBUTES](#) 17

[AUTHZR_TOKEN_GROUPS](#) 17

[AUTHZR_TOKEN_USER](#) 18

[overview](#) 13

[SR_SD](#) 18

T

Timer events

server

[authzr](#) 29

Timers

server

[authzr](#) 19

[Tracking changes](#) 39

[Transport](#) 9

V

[Vendor extensible fields](#) 8

[Versioning](#) 7